

Plug-in API

On this page:

- [The Plugin Interface](#)
- [C++ Plug-in Factory](#)
- [Java Plug-in Factory](#)
- [C# Plug-in Factory](#)

The Plugin Interface

The plug-in facility defines a [local](#) Slice interface that all plug-ins must implement:

Slice

```
module Ice {
  local interface Plugin {
    void initialize();
    void destroy();
  };
};
```

The lifecycle of an Ice plug-in is structured to accommodate dependencies between plug-ins, such as when a logger plug-in needs to use IceSSL for its logging activities. Consequently, a plug-in object's lifecycle consists of four phases:

- **Construction**
The Ice run time uses a language-specific factory API for instantiating plug-ins. During construction, a plug-in can acquire resources but must not spawn new threads or perform activities that depend on other plug-ins.
- **Initialization**
After all plug-ins have been constructed, the Ice run time invokes `initialize` on each plug-in. The order in which plug-ins are initialized is undefined by default but can be [customized](#) using a configuration property. If a plug-in has a dependency on another plug-in, you must configure the Ice run time so that initialization occurs in the proper order. In this phase it is safe for a plug-in to spawn new threads; it is also safe for a plug-in to interact with other plug-ins and use their services, as long as those plug-ins have already been initialized. If `initialize` raises an exception, the Ice run time invokes `destroy` on all plug-ins that were successfully initialized (in the reverse order of initialization) and raises the original exception to the application.
- **Active**
The active phase spans the time between initialization and destruction. Plug-ins must be designed to operate safely in the context of multiple threads.
- **Destruction**
The Ice run time invokes `destroy` on each plug-in in the reverse order of initialization.

This lifecycle is repeated for each new communicator that an application creates and destroys.

C++ Plug-in Factory

In C++, the plug-in factory is an exported function with C linkage having the following signature:

C++

```
extern "C"
{
  ICE_DECLSPEC_EXPORT Ice::Plugin*
  functionName(const Ice::CommunicatorPtr& communicator,
               const std::string& name,
               const Ice::StringSeq& args);
}
```

You can define the function with any name you wish. We recommend that you use the `ICE_DECLSPEC_EXPORT` macro to ensure that the function is exported correctly on all platforms. Since the function uses C linkage, it must return the plug-in object as a regular C++ pointer and not as an Ice smart pointer. Furthermore, the function must not raise C++ exceptions; if an error occurs, the function must return zero.

The arguments to the function consist of the communicator that is in the process of being initialized, the name assigned to the plug-in, and any arguments that were specified in the [plug-in's configuration](#).

Java Plug-in Factory

In Java, a plug-in factory must implement the `Ice.PluginFactory` interface:

Java

```
package Ice;

public interface PluginFactory {
    Plugin create(Communicator communicator, String name, String[] args);
}
```

The arguments to the `create` method consist of the communicator that is in the process of being initialized, the name assigned to the plug-in, and any arguments that were specified in the [plug-in's configuration](#).

The `create` method can return `null` to indicate that a general error occurred, or it can raise `PluginInitializationException` to provide more detailed information. If any other exception is raised, the Ice run time wraps it inside an instance of `PluginInitializationException`.

C# Plug-in Factory

In .NET, a plug-in factory must implement the `Ice.PluginFactory` interface:

C#

```
namespace Ice {
    public interface PluginFactory
    {
        Plugin create(Communicator communicator, string name, string[] args);
    }
}
```

The arguments to the `create` method consist of the communicator that is in the process of being initialized, the name assigned to the plug-in, and any arguments that were specified in the [plug-in's configuration](#).

The `create` method can return `null` to indicate that a general error occurred, or it can raise `PluginInitializationException` to provide more detailed information. If any other exception is raised, the Ice run time wraps it inside an instance of `PluginInitializationException`.

See Also

- [Plug-in Configuration](#)
- [Advanced Plug-in Topics](#)