Ice Trace Properties

On this page:

- Ice.Trace.GC
- Ice.Trace.Locator
- Ice.Trace.Network
- Ice.Trace.Protocol
- Ice.Trace.Retry
- Ice.Trace.Slicing
- Ice.Trace.ThreadPool

Ice.Trace.GC

Synopsis

Ice.Trace.GC=num

Description

Ice for C++ includes a garbage collector for Slice objects. This property controls the trace level for the garbage collector:

- 0 No garbage collector trace (default).
- Show the total number of instances collected, the total number of instances examined, the time spent in the collector in milliseconds, and the total number of runs of the collector.
- 2 Like 1, but also produces a trace message for each run of the collector.

Ice.Trace.Locator

Synopsis

Ice.Trace.Locator=num

Description

The Ice run time makes locator requests to resolve the endpoints of object adapters and well-known objects. Requests on the locator registry are used to update object adapter endpoints and set the server process proxy. This property controls the trace level for the Ice run time's interactions with the locator:

- 0 No locator trace (default).
- 1 Trace Ice locator and locator registry requests.
- 2 Like 1, but also trace the removal of endpoints from the cache.

Ice.Trace.Network

Synopsis

Ice.Trace.Network=num

Description

Controls the trace level for low-level network activities such as connection establishment and read/write operations:

- 0 No network trace (default).
- 1 Trace successful connection establishment and closure.
- 2 Like 1, but also trace attempts to bind, connect, and disconnect sockets.

Like 2, but also trace data transfer, the published endpoints for an object adapter, and the current list of local addresses for an endpoint that uses the wildcard address.

Ice.Trace.Protocol

Synopsis

Ice.Trace.Protocol=num

Description

Controls the trace level for Ice protocol mesages:

No protocol trace (default).Trace Ice protocol messages.

Ice.Trace.Retry

Synopsis

Ice.Trace.Retry=num

Description

Ice supports automatic retries in case of a request failure. This property controls the trace level for retry attempts:

0	No request retry trace (default).
1	Trace Ice operation call retries.
2	Also trace Ice endpoint usage.

Ice.Trace.Slicing

Synopsis

Ice.Trace.Slicing=num

Description

The Ice data encoding for exceptions and classes enables a receiver to slice an unknown exception or class type to a known type. This property controls the trace level for slicing activities:

0	No trace of slicing activity (default).
1	Trace all exception and class types that are unknown to the receiver and therefore sliced.

Ice.Trace.ThreadPool

Synopsis

Ice.Trace.ThreadPool=num

Description

Controls the trace level for the Ice thread pool:

0 No trace of thread pool activity (default).

1 Trace the creation, growing, and shrinking of thread pools.