

IceGrid Administrative Client Properties

On this page:

- [IceGridAdmin.AuthenticateUsingSSL](#)
- [IceGridAdmin.Password](#)
- [IceGridAdmin.Replica](#)
- [IceGridAdmin.Trace.Observers](#)
- [IceGridAdmin.Trace.SaveToRegistry](#)
- [IceGridAdmin.Username](#)

IceGridAdmin.AuthenticateUsingSSL

Synopsis

`IceGridAdmin.AuthenticateUsingSSL=num`

Description

If *num* is a value greater than zero, [icegridadmin](#) uses SSL authentication when establishing its session with the IceGrid registry. If not defined or the value is zero, [icegridadmin](#) uses user name and password authentication.

IceGridAdmin.Password

Synopsis

`IceGridAdmin.Password=password`

Description

Specifies the password that [icegridadmin](#) should use when authenticating its session with the IceGrid registry. For security reasons you may prefer not to define a password in a plain-text configuration property, in which case you should omit this property and allow [icegridadmin](#) to prompt you for it interactively. This property is ignored when SSL authentication is enabled via [#IceGridAdmin.AuthenticateUsingSSL](#).

IceGridAdmin.Replica

Synopsis

`IceGridAdmin.Replica=name`

Description

Specifies the name of the [registry replica](#) that [icegridadmin](#) should contact. If not defined, the default value is `Master`.

IceGridAdmin.Trace.Observers

Synopsis

`IceGridAdmin.Trace.Observers=num`

Description

If *num* is a value greater than zero, the IceGrid graphical administrative client displays trace information about the observer callbacks it receives from the registry. If not defined, the default value is zero.

IceGridAdmin.Trace.SaveToRegistry

Synopsis

`IceGridAdmin.Trace.SaveToRegistry=num`

Description

If *num* is a value greater than zero, the IceGrid graphical administrative client displays trace information about the modifications it commits to the registry. If not defined, the default value is zero.

IceGridAdmin.Username

Synopsis

`IceGridAdmin.Username=name`

Description

Specifies the username that `icegridadmin` should use when authenticating its session with the IceGrid registry. This property is ignored when SSL authentication is enabled via `#IceGridAdmin.AuthenticateUsingSSL`.