

Ice-LocatorRegistry

Ice::LocatorRegistry

Overview

interface LocatorRegistry

The Ice locator registry interface. This interface is used by servers to register adapter endpoints with the locator.

The [Ice::LocatorRegistry](#) interface is intended to be used by Ice internals and by locator implementations. Regular user code should not attempt to use any functionality of this interface directly.

Operation Index

[setAdapterDirectProxy](#) — Set the adapter endpoints with the locator registry.
[setReplicatedAdapterDirectProxy](#) — Set the adapter endpoints with the locator registry.
[setServerProcessProxy](#) — Set the process proxy for a server.

Operations

["amd"] void setAdapterDirectProxy(string id, Object* proxy) throws [Ice::AdapterNotFoundException](#), [Ice::AdapterAlreadyActiveException](#)

Set the adapter endpoints with the locator registry.

Parameters

`id` — The adapter id.
`proxy` — The adapter proxy (a dummy direct proxy created by the adapter). The direct proxy contains the adapter endpoints.

Exceptions

[Ice::AdapterNotFoundException](#) — Raised if the adapter cannot be found, or if the locator only allows registered adapters to set their active proxy and the adapter is not registered with the locator.
[Ice::AdapterAlreadyActiveException](#) — Raised if an adapter with the same id is already active.

["amd"] void setReplicatedAdapterDirectProxy(string adapterId, string replicaGroupId, Object* p) throws [Ice::AdapterNotFoundException](#), [Ice::AdapterAlreadyActiveException](#), [Ice::InvalidReplicaGroupIdException](#)

Set the adapter endpoints with the locator registry.

Parameters

`adapterId` — The adapter id.
`replicaGroupId` — The replica group id.
`p` — The adapter proxy (a dummy direct proxy created by the adapter). The direct proxy contains the adapter endpoints.

Exceptions

[Ice::AdapterNotFoundException](#) — Raised if the adapter cannot be found, or if the locator only allows registered adapters to set their active proxy and the adapter is not registered with the locator.
[Ice::AdapterAlreadyActiveException](#) — Raised if an adapter with the same id is already active.
[Ice::InvalidReplicaGroupIdException](#) — Raised if the given replica group doesn't match the one registered with the locator registry for this object adapter.

["amd"] void setServerProcessProxy(string id, [Ice::Process*](#) proxy) throws [Ice::ServerNotFoundException](#)

Set the process proxy for a server.

Parameters

`id` — The server id.
`proxy` — The process proxy.

Exceptions

[Ice::ServerNotFoundException](#) — Raised if the server cannot be found.
