

# IceGrid Administrative Client Properties

On this page:

- [IceGridAdmin.AuthenticateUsingSSL](#)
- [IceGridAdmin.Password](#)
- [IceGridAdmin.Replica](#)
- [IceGridAdmin.Trace.Observers](#)
- [IceGridAdmin.Trace.SaveToRegistry](#)
- [IceGridAdmin.Username](#)

## [IceGridAdmin.AuthenticateUsingSSL](#)

### Synopsis

```
IceGridAdmin.AuthenticateUsingSSL=num
```

### Description

If *num* is a value greater than zero, `icegridadmin` uses SSL authentication when establishing its session with the IceGrid registry. If not defined or the value is zero, `icegridadmin` uses user name and password authentication.

## [IceGridAdmin.Password](#)

### Synopsis

```
IceGridAdmin.Password=password
```

### Description

Specifies the password that `icegridadmin` should use when authenticating its session with the IceGrid registry. For security reasons you may prefer not to define a password in a plain-text configuration property, in which case you should omit this property and allow `icegridadmin` to prompt you for it interactively. This property is ignored when SSL authentication is enabled via `#IceGridAdmin.AuthenticateUsingSSL`.

## [IceGridAdmin.Replica](#)

### Synopsis

```
IceGridAdmin.Replica=name
```

### Description

Specifies the name of the `registry replica` that `icegridadmin` should contact. If not defined, the default value is `Master`.

## [IceGridAdmin.Trace.Observers](#)

### Synopsis

```
IceGridAdmin.Trace.Observers=num
```

### Description

If *num* is a value greater than zero, the IceGrid graphical administrative client displays trace information about the observer callbacks it receives from the registry. If not defined, the default value is zero.

## [IceGridAdmin.Trace.SaveToRegistry](#)

### Synopsis

```
IceGridAdmin.Trace.SaveToRegistry=num
```

### Description

If *num* is a value greater than zero, the IceGrid graphical administrative client displays trace information about the modifications it commits to the registry. If not defined, the default value is zero.

## **IceGridAdmin.Username**

### Synopsis

```
IceGridAdmin.Username=name
```

### Description

Specifies the username that `icegridadmin` should use when authenticating its session with the IceGrid registry. This property is ignored when SSL authentication is enabled via `#IceGridAdmin.AuthenticateUsingSSL`.